



AIR TRAVEL

Wireframes for mobile




OBJECTIVES

Further refine the digital prototype for users flowing through and completing the task of booking a flight.

To define the details required for developers to build the app accurately.

1

Notifications



On selection dialogue box closes and user brought to home screen (2).


On selection browser window opens and user is brought to portion of website outlining COVID-19 updates and travel information.

2

Home Screen

Typical Menu: Appears on every standard screen (not including dialogue boxes).

- Home icon: On selection user is brought to Home Screen.
- Deals icon: On selection user is brought to screen showing current deals and promotions.
- Account icon: On selection user is brought to log in screen if not already signed in. If user is logged in, displays list of booked flights and other account information.
- More icon: On selection, drawer menu appears from the right-hand side displaying other app functions.



On selection user brought to Flight Search screen (3.1).

On selection user brought to list of booked flights if user is logged in, if not, user brought to log in screen.

On selection user brought to log in screen. Button not visible if already signed in.

3.1

Flight Search

Typical Indicator Bar:

Indicator bar at top of each screen tracking booking progress (not including dialogue boxes.)

Automatically populates with closest airport based on GPS location. On selection user brought to departure city dialogue box (3.2.1). Changes to input from departure city dialogue box once selection process is complete.

Automatically populates with most recent search date. On selection user brought to calendar dialogue box (3.3). Changes to input from calendar dialogue box once selection process is complete.

Defaults to 1 Adult. On selection user brought to passengers dialogue box (3.4). Changes to input from passengers dialogue box once selection process is complete. Field will expand to show all passenger types if more than one type selected.

The image shows a mobile app interface for flight search. At the top, there's a status bar with the time 9:41 and signal/battery icons. Below it is a header bar with a blue background and white text 'Let's Go!' and a flight icon. The main title 'Flight Search' is centered. Below the title are three tabs: 'Round Trip' (highlighted in blue), 'One Way', and 'Multi-City'. The 'From:' field is populated with 'Edmonton Int'l Airport (YEG)'. The 'To:' field is populated with 'Winnipeg Int'l Airport (YWG)'. The 'Depart:' field is populated with 'September 1, 2021'. The 'Return:' field is populated with 'September 14, 2021'. The 'Passengers:' field is populated with '1 Adult'. The 'Promo Code:' field is labeled '(Optional)'. At the bottom is a blue button with the text 'SEARCH >'. The bottom navigation bar has four icons: 'Home', 'Deals', 'Account', and 'More'.

Round Trip – Is shown as default setting. Blue highlighting changes to black when another tab is selected.

One Way – On selection tab is highlighted in blue and brought to the front and “Return” date is removed from available fields.

Multi-City – On selection tab is highlighted in blue and brought to the front and additional fields are provided to allow for selection of additional airports and dates.

Automatically populates with most recent search. On selection user brought to return city dialogue box (3.2.2). Changes to input from return city dialogue box once selection process is complete.



Automatically populates with most recent search. On selection user brought to calendar dialogue box (3.3). Changes to input from calendar dialogue box once selection process is complete.

‘(Optional)’ text is shown in gray. On selectin user brought to promo code dialogue box. Changes to input from promo code dialogue box once process is complete.

Button will be grey if required fields are incomplete (for example, during first time using app and therefore no recent searches). On selection brings user to departure flights screen (4.1).

3.2.1 / 2

To/From Dialogue Box



Displays nearby airports based on GPS location.

Closes dialogue box and returns user to flight search screen (3.1).

Shows blinking cursor. Once user begins to type, field will expand to include drop down menu showing options based on closest matches to text entered.


Displays most frequently searched destinations. Will not appear if no recent searches made (for example, during first time using app).

Displays recent searches. Will not appear if no recent searches made (for example, during first time using app).

QWERTY keyboard appears. Selecting 'Enter' on keyboard will hide keyboard.

On selection user returns to flight search screen (3.1). City selection made populates relevant field.



Dates Dialogue Box



On selection, next month will display, and information will slide up.

3.4

Passengers Dialogue Box



Defaults to 1 Adult.

Is highlighted in blue when option is available. For example, if there is no value shown, (-) is grayed out. On selection decreases by one the value of the passenger number field.

Closes dialogue box and returns user to flight search screen (3.1).

On selection increases by one the value of the passenger number field.

On selection user returns to flight search screen (3.1) .

On selection user is brought to a dialogue box with detailed information about traveling with infants.

4.1.1


Departure Flights

Back arrow: On selection user returns to flight search screen (3.1).

Sort by: Time: Highlighted in blue to indicate default sort. Button becomes black/white when another Sort by button is selected. Flights are displayed in order of departure time with non-stop flights showing before flights with stopovers.

Sort by: \$: On selection will be highlighted in blue and flight options will reorganize to display lowest fare at the top.

Sort by: Duration: On selection will be highlighted in blue and flight options will reorganize to display shortest trip at the top.



Displays date and lowest fare for that date. Defaults to departure date selected during flight search (middle tab) and is indicated with blue highlighting. Left tab displays date previous and right tab displays date after. Blue outline appears and tab is brought to the front when selected.

Flights: On selection user will be taken to fare option dialogue box (4.1.2).

4.1.2

Departure Flights

9:41

Choose your fare ✕

Departing Flight
November 11, 2021

07:00 YEG EDMONTON 3h 38m Non-stop YYZ TORONTO 12:38 \$300 CAD per passenger

ECONOMY

| BASIC | PLUS |
|---|---|
| <ul style="list-style-type: none">No FlyUX Rewards earnChecked bags for a feeNo changes/cancellationsNo seat selectionNo BIZlounge access | <ul style="list-style-type: none">FlyUX Rewards earnChecked bags for a feeChange/cancel for a feeSeat selection for a feeBIZlounge access for a fee |
| SELECT \$300 | SELECT \$375 |

BUSINESS CLASS

| BUSINESS | BIZPLUS |
|--|---|
| <ul style="list-style-type: none">FlyUX Rewards earnFree checked bagsOne time change on feeBusiness Class seatBIZlounge access for a fee | <ul style="list-style-type: none">FlyUX Rewards earnFree checked bagsNo fee cancellationsBusiness Class seatAccess to BIZlounge |
| SELECT \$500 | SELECT \$595 |

CONTINUE >

Closes dialogue box and returns user to departure flight screen (4.1.1).

On selection button is highlighted in blue.

Is greyed out and becomes highlighted once a fare option is selected. On selection user proceeds to return flight screen (4.2.1).

4.2.1


Return Flights

Back arrow: On selection user returns to departure flights screen (4.1.1).

Sort by: Time: Highlighted in blue to indicate default sort. Button becomes black/white when another Sort by button is selected. Flights are displayed in order of departure time with non-stop flights showing before flights with stopovers.

Sort by: \$: On selection will be highlighted in blue and flight options will reorganize to display lowest fare at the top.

Sort by: Duration: On selection will be highlighted in blue and flight options will reorganize to display shortest trip at the top.



Displays date and lowest fare for that date. Defaults to departure date selected during flight search (middle tab) and is indicated with blue highlighting. Left tab displays date previous and right tab displays date after. Blue outline appears and tab is brought to the front when selected.

Flights: On selection user will be taken to fare option dialogue box (4.2.2).

4.2.2

Return Flights

9:41

Choose your fare
Return Flight
November 21, 2021

20:55 YYZ TORONTO 4h 07m Non-stop 23:02 YEG EDMONTON \$300 CAD per passenger

ECONOMY

| BASIC | PLUS |
|--|--|
| <ul style="list-style-type: none">No FlyUX Rewards earnChecked bags for a feeNo changes/cancellationsNo seat selectionNo BiZ lounge access | <ul style="list-style-type: none">FlyUX Rewards earnChecked bags for a feeChange/cancel for a feeSeat selection for a feeBiZ lounge access for a fee |
| SELECT \$300 | SELECT \$375 |

BUSINESS CLASS

| BUSINESS | BIZPLUS |
|---|--|
| <ul style="list-style-type: none">FlyUX Rewards earnFree checked bagsOne time change on feeBusiness Class seatBiZ lounge access for a fee | <ul style="list-style-type: none">FlyUX Rewards earnFree checked bagsNo fee cancellationsBusiness Class seatAccess to BiZ lounge |
| SELECT \$500 | SELECT \$595 |

CONTINUE >

Closes dialogue box and returns user to return flight screen (4.2.1).

On selection button is highlighted in blue.


Is greyed out and becomes highlighted once a fare option is selected. On selection user proceeds to flight summary screen (4.3).

4.3

Flight Summary

Back arrow: On selection user returns to return flights screen (4.2.1).

On selection user is brought to screen with options to share flight summary. Available options based on device operating system and relevant apps installed on device.




On selection user is brought to screen with option to save flight within app. User will be brought to log in screen if not already signed in.

On selection user is brought to sign in screen (5.1) or if already signed in brings user directly to passenger info screen (5.2).

5.1

Sign In Screen

Back arrow: On selection user returns to flight summary screen (4.3).



On selection user brought to log in screen.

On selection user is brought to sign up form screen.

On selection use is brought to passenger info screen (5.2).

5.2

Passenger Info

Back arrow: On selection user returns to sign in screen (5.1).

On selection, blinking cursor appears in field and QWERTY keypad appears.

On selection, blinking cursor appears in field and NUMBER keypad appears. Field for country code will appear before phone field for international flights only.

Down arrow: Appears only when there are portions of the form not visible on the screen. On selection, information will slide up.

The screenshot shows a mobile app interface for entering passenger information. At the top, there's a status bar with the time 9:41 and signal/battery icons. Below is a progress indicator with five circles, the second of which is filled blue. The form consists of two identical sections for 'Passenger #1' and 'Passenger #2'. Each section starts with a dropdown menu currently set to 'ADULT'. Below this are four text input fields: 'First Name:', 'Last Name:', 'Email:', and 'Phone:'. The 'Phone:' field has a small icon of a phone handset to its left. Below the 'Phone:' field is a field for 'Loyalty Program #:' with '(Optional)' text to its right. Below that is a dropdown menu for 'Special Requirements'. At the bottom of the form is a large grey button labeled 'CONTINUE' with a right-pointing arrow. Above this button is a large downward-pointing chevron icon. At the very bottom is a navigation bar with four icons: a house for 'Home', a ticket for 'Deals', a person for 'Account', and three dots for 'More'.

Defaults to Adult. On selection of arrow, selection panel animates to expand to open state.

On selection, blinking cursor appears in field and QWERTY keypad appears.

On selection, blinking cursor appears in field and QWERTY keypad appears.

On selection, blinking cursor appears in field and NUMBER keypad appears.

On selection of arrow, selection panel animates to expand to open state showing options.

Remains grey until all required information on form is filled in.

5.3

Passenger Type

Back arrow: On selection user returns to previous screen state.

9:41

Passenger #1

ADULT
CHILD
INFANT

First Name:

Last Name:

Email:

Phone:

Loyalty Program #: (Optional)

Special Requirements

Passenger #2

ADULT

First Name:

Last Name:

Email:

Phone:

CONTINUE

Home Deals Account More

On selection panel animates to expand to open state or contract to closed state – arrow direction changes accordingly to indicate open/close. On selection, passenger type (Adult, Child or Infant) is highlighted in orange. When collapsed, only selected passenger type will show in field.

Down arrow: Appears only when there are portions of the form not visible on the screen. On selection, information will slide up.

Remains grey until all required information on form is filled in.

5.4

Enter Name/Email

Back arrow: On selection user returns to previous screen state.

On selection a blinking cursor appears in field and an EMAIL keyboard appears. Selecting 'Enter' on keyboard will confirm text, moving cursor to next field and keyboard type will change as required.

The image shows a mobile application interface for entering passenger information. At the top, there is a status bar with the time 9:41, signal strength, and battery level. Below the status bar is a navigation bar with a back arrow and a progress indicator consisting of six circles, with the second circle highlighted in blue. The form is divided into two sections for Passenger #1 and Passenger #2. Each section has a dropdown menu for 'ADULT' and a series of text input fields for 'First Name', 'Last Name', 'Email', 'Phone', and 'Loyalty Program #'. The 'Email' field is currently selected, and a QWERTY keyboard is visible at the bottom of the screen. The keyboard has a 'Go' button on the right. The form is annotated with three pink boxes and arrows explaining the back arrow, the email keyboard, and the 'Enter' key functionality.

On selection a blinking cursor appears in field and QWERTY keyboard appears. Selecting 'Enter' on keyboard will confirm text, moving cursor to next field and keyboard type will change as required.

5.5

Enter Phone/Loyalty

9:41

< ● ● ● ● ● ●

Passenger #1 **ADULT** ▼

First Name: Jane

Last Name: Doe

Email: janeydoe123@gmail.com

Phone: _

Loyalty Program #: (Optional)

Special Requirements ▼

Passenger #2 **ADULT** ▼

First Name:

Last Name:

1 2 3
4 5 6
7 8 9
0

9:41

< ● ● ● ● ● ●

Passenger #1 **ADULT** ▼

First Name: Jane

Last Name: Doe

Email: janeydoe123@gmail.com

Phone: (780) 555-5555

Loyalty Program #: (Optional)

Special Requirements ▼

Passenger #2 **ADULT** ▼

First Name:

Last Name:

Email:

Phone:

Loyalty Program #: (Optional)

✓ **CONTINUE** >

Home Deals Account More

Back arrow: On selection user returns to previous screen state.

On selection a blinking cursor appears in field and NUMBER pad appears. Digits autoformat to standard 10-digit telephone number (###) ###-####. Selecting 'Enter' will confirm text and move cursor to next field with a change keyboard type as required.

On selection a blinking cursor appears in field and NUMBER pad appears. Selecting 'Enter' will confirm text and close NUMBER pad.

Remains grey until all required information on form is filled in.

5.6

Assistance Info

9:41

Passenger #1 **ADULT** ▾

First Name: Jane

Last Name: Doe

Email: janeydoe123@gmail.com

Phone: (780) 555-5555

Loyalty Program #: (Optional)

Special Requirements ⬆

- Wheelchair Service ☒
- Hearing Assist ☐
- Vision Assist ☐
- Cognitive & Developmental Assist ☐
- Travelling with Service Animal ☐
- Severe Allergies ☒
- Unaccompanied Minor ☐

Passenger #2 **ADULT** ▾

✓ **CONTINUE** >

Home Deals Account More

9:41

Passenger #1 **ADULT** ▾

First Name: Jane

Last Name: Doe

Email: janeydoe123@gmail.com

Phone: (780) 555-5555

Loyalty Program #: (Optional)

Special Requirements ▾

- Wheelchair Service ☒
- Severe Allergies ☒
- Unaccompanied Minor ☐

Passenger #2 **ADULT** ▾

First Name:

Last Name:

Email:

✓ **CONTINUE** >

Home Deals Account More

Back arrow: On selection user returns to previous screen state.

On selection panel animates to expand to open state or contract to closed state – arrow type changes accordingly to indicate open/close. If options are selected, options will appear as list in closed state.

On selection the circle next to special requirement option changes to green and a checkmark becomes visible.

On selection user is brought to a dialogue box with detailed information with definitions of each item listed as a special requirement.

Remains grey until all required information on form is filled in.

5.7

Passenger Info

Back arrow: On selection user returns to previous screen state.

Appears only when there are options on the form not shown above the visible section of the screen. On selection, information will slide down. Swiping down will also reveal hidden information.

Shows last name.

Shows phone # in standard 10-digit format (###) ###-####.

Down arrow: Appears only when there are portions of the form not shown below the current visible section of the screen. On selection, information will slide up. Swiping up will also reveal hidden information.

The form is displayed on a mobile screen with a status bar at the top showing the time 9:41 and signal/battery icons. The form itself has a progress indicator at the top with five circles, the second of which is filled blue. Below this is a back arrow and a down arrow. The form fields are as follows:

- Phone:** (780) 555-5555
- Loyalty Program #:** (Optional)
- Special Requirements:** A dropdown menu currently showing a list of options: "Wheelchair Service" and "Severe Allergies", both with green checkmarks.
- Passenger #2:** A dropdown menu currently showing "ADULT".
- First Name:** John
- Last Name:** Doe
- Email:** johndog456@gmail.com
- Phone:** (780) 555-5555
- Loyalty Program #:** (Optional)
- Special Requirements:** A dropdown menu currently showing a list of options.

At the bottom of the form is a large blue button with the text "CONTINUE" and a right-pointing arrow. Below the form is a bottom navigation bar with four icons: a house for "Home", a tag for "Deals", a person for "Account", and three dots for "More".

Selected options show as list.

Shows passenger type.

Shows first name.

Shows email.


Shows loyalty program # if entered.

Remains grey until all required information on form is filled in. Once information is complete is highlighted in blue.

5.8

Passenger Summary

Back arrow: On selection user returns to passenger info screen (5.7).



On selection user is brought to seat selection screen (6.1).

6.1

Seat Selection

Back arrow: On selection user returns to passenger summary screen (5.8).

9:41

< ● ● ● ○ ○ ○ ○ ○

Choose your seats

Departing Flight

07:00 ○ 12:38 ○
YEG YYZ
EDMONTON TORONTO
3h 38m
Non-stop

Passenger #1 **SELECT**

Passenger #2 **SELECT**

Return Flight

20:55 ○ 23:02 ○
YYZ YEG
TORONTO EDMONTON
4h 07m
Non-stop

Passenger #1 **SELECT**

Passenger #2 **SELECT**

CONTINUE >

Home Deals Account More

On selection user is brought to seat dialogue box (6.2) featuring seat map. Buttons change to blue and text shows seat chosen once seat selection process has taken place through the seat dialogue box (6.2).

On selection user is brought to flight extras screen (7.1).

6.2

Seat Dialogue Box

9:41

Choose your seats (Close icon)

Departing Flight
Passenger #1

EXIT

| A | C | D | F |
|------|------|--------|------|
| | | 1 \$90 | \$90 |
| \$90 | \$90 | 2 \$90 | \$90 |
| | \$90 | 3 | \$90 |

A B C D E F

| | | | | | |
|------|------|------------|------|------|------|
| \$20 | \$20 | P1 13 \$20 | \$20 | \$20 | \$20 |
| \$20 | | 14 | \$20 | | |
| \$20 | \$20 | 15 | | \$20 | |
| \$20 | \$20 | 16 | \$20 | \$20 | \$20 |

CONTINUE >

9:41

Choose your seats (Close icon)

Return Flight
Passenger #2

Same seat as Departing Flight

EXIT

| A | C | D | F |
|------|------|--------|------|
| | | 1 \$90 | \$90 |
| \$90 | \$90 | 2 \$90 | \$90 |
| | \$90 | 3 | \$90 |

A B C D E F

| | | | | | |
|------|------|------------|------|------|------|
| \$20 | \$20 | P1 13 \$20 | \$20 | \$20 | \$20 |
| \$20 | | 14 | \$20 | | |
| \$20 | \$20 | 15 | | \$20 | |
| \$20 | \$20 | 16 | \$20 | \$20 | \$20 |

CONTINUE >

Closes dialogue box and returns user to seat selection screen (6.1). Selections are not preserved.

Same seat button only appears when return flight seats are being chosen and same seat as departing flight is available. On selection, same seat as departing flight is highlighted in seat map.

When selecting seat for second passenger, seat for first passenger is highlighted in seat map.

Appears only when there are portions of the form not shown below the current visible section of the screen. On selection, information will slide up. Swiping up will also reveal hidden information.

Is grey until selection is made. On selection user is brought back to seat selection screen (6.1).

Seat is highlighted in blue once selected. Text indicates which passenger seat has been assigned to. For example, P1 = Passenger #1.

7.1

Fight Extras

Back arrow: On selection user returns to previous screen state.

On selection a dialogue box to select insurance options appears (7.3). Shows type and cost of insurance once selected or indicates 'no insurance' if no insurance selected.

On selection a dialogue box to coordinate a car rental appears. Shows type and cost of rental once selected or 'no rental' if no car rental selected.

9:41

Flight Extras

Passenger #1

Baggage: 1 bag +\$20 each way

Insurance: Emerg. Medical +\$100

Food Vouchers: No vouchers

Car Rental: No rental

Passenger #2

Baggage: No baggage

Insurance: Emerg. Medical +\$100

Food Vouchers: Voucher +\$20

Car Rental: No rental

CONTINUE >

Home Deals Account More



On selection a dialogue box for baggage selection appears (7.2). Shows number and cost of bags once selected or indicates 'no baggage' if no bags selected.

On selection a dialogue box to select from food voucher options appears. Shows type and value of voucher once selected or indicates 'no vouchers' if no food vouchers selected.

Remains grey until all fields on the form are filled in. Once information is complete is highlighted in blue and can be selected. On selection user is brought to cost summary screen (8.1).

7.2

Baggage Option



On selection user is brought to a dialogue box with detailed information about baggage fees.

Closes dialogue box and returns user to flight extras screen (7.1).

On selection increases by one the value of the baggage number field.



Cost updates based on options selected.

On selection user returns to flight extras screen (7.1).

Is highlighted in blue when option is available. For example, if there is no value shown, (-) is grayed out. On selection decreases by one the value of the baggage number field.

7.3

Travel Insurance



Closes dialogue box and returns user to flight extras screen (7.1).

On selection the circle next to insurance options changes to green and a checkmark is visible.

Cost updates based on options selected.

On selection user returns to flight extras screen (7.1)

On selection user is brought to a dialogue box with definitions and detailed information on each insurance option and how costs are calculated.

8.1

Cost Summary

Back arrow: On selection user returns to flight extras (7.1)

9:41

Cost Summary

Departing Flight
November 11, 2021
07:00 depart, Edmonton (YEG)
12:38 arrival, Toronto (YYZ)
3h38m Non-stop
\$250.90 Flight
\$ 12.50 Taxes
\$ 37.50 Airport Fee
\$300 per person

Return Flight
November 21, 2021
20:55 depart, Toronto (YYZ)
23:02 arrival, Edmonton (YEG)
4h07m Non-stop
\$250.90 Flight
\$ 12.50 Taxes
\$ 37.50 Airport Fee
\$300 per person

Adults x2 **\$1200**
Jane Doe
John Doe

Seat Selection (x4) **\$80**
Departing Flight: 13C, 13D
Return Flight: 13C, 13D

Baggage Fees (x1 bag) **\$40**

Insurance (x2) **\$200**
Emergency Medical: Jane Doe
Emergency Medical: John Doe

Food Vouchers (x2) **\$20**

GRAND TOTAL **\$1540**
Canadian Dollar (CAD)

PAY NOW >

Home Deals Account More

On selection user is brought to payment options screen (8.2) .

8.2

Payment Options

Back arrow: On selection user returns to cost summary (8.1)



Payment method icons: On selection user is taken to a screen showing fields appropriate for the payment type. For example, Mastercard users will see Credit Card entry screen (8.3)


8.3

Payment Screen

Back arrow: On selection user returns previous screen state.

Sample text is shown in grey until information is input. On selection NUMBER pad appears (8.4). Shows card number in standard 16-digit credit card number format #### #### ## #### once entered.

Sample text is shown in grey until information is input. On selection NUMBER pad appears (8.4). Shows expiry date in standard 4-digit credit card expiry date format ##/## once entered.



The image shows a mobile app payment screen. At the top, there's a status bar with the time 9:41, signal strength, Wi-Fi, and battery icons. Below the status bar is a navigation bar with a back arrow and four dots, the third of which is highlighted in blue. The main content area has the title 'Total Payment' and a large amount '\$1540.00 CAD'. Below this is a MasterCard logo. There are four input fields: 'Card#' with the value '5191-0000-0000-0000', 'Exp:' with '05/23', 'Sec ID:' with '000' and a small circular icon to its right, and 'Name:' with 'Jane Doe'. At the bottom of the main content area is a large blue button labeled 'CONFIRM' with a right-pointing chevron. The bottom of the screen features a blue navigation bar with four icons: a house for 'Home', a card for 'Deals', a person for 'Account', and three dots for 'More'.

Sample text is shown in grey until information is input. On selection NUMBER pad appears (8.4). Shows security ID number in standard 3-digit security ID format ###.

On selection QWERTY keypad appears (8.4). Shows name of cardholder. Once entered.

Once information is complete is highlighted in blue and can be selected. On selection user is brought to confirmation screen (9).

8.4

Enter Exp/Sec ID

Back arrow: On selection user returns previous screen state.

Sample text is shown in grey until information is input. On selection a blinking cursor appears in field and NUMBER pad appears. Digits autoformat to standard 16-digit credit card number length #####-####-####-####. When 'Enter' on NUMBER pad is selected, cursor moves to Exp: field.

Sample text is shown in grey until information is input. On selection a blinking cursor appears in field and NUMBER pad appears. Digits autoformat to standard 4-digit credit card expiry date format ##/##. When 'Enter' on NUMBER pad is selected, cursor moves to Sec ID: field.

The image shows a mobile app interface for entering payment information. At the top, there's a status bar with the time 9:41 and signal/battery icons. Below that is a progress indicator with five dots, the fourth of which is highlighted in blue. A back arrow is to the left of the progress indicator. The main heading is "Total Payment" in bold black text. Below that is the amount "\$1540.00 CAD" in large bold black text. Underneath is a MasterCard logo. There are four input fields: "Card#:" with the value "5191-0000-0000-0000", "Exp:" with the value "05/23", "Sec ID:" with the value "000", and "Name:". Each field has a blinking cursor at the end. Below the input fields is a numeric keypad with digits 1-9, 0, and a backspace key (X). The keypad is styled with grey buttons and black text.

On selection user is brought to a dialogue box with information about where to find security ID on credit card.

Sample text is shown in grey until information is input. On selection a blinking cursor appears in field and NUMBER pad appears. Digits autoformat to standard 3-digit security ID format ###. NUMBER pad is hidden when 'Enter' is selected.

8.5

Enter Name

Back arrow: On selection user returns previous screen state.

A mobile app screen titled "Total Payment" showing a payment amount of "\$1540.00 CAD". Below the amount is a MasterCard logo. The screen contains three input fields: "Card#: 5191-0000-0000-0000", "Exp: 05/23", and "Sec ID: 000". At the bottom is a "Name:" input field with a blinking cursor. A QWERTY keyboard is visible at the bottom of the screen. The status bar at the top shows the time 9:41 and signal strength.


On selection a blinking cursor appears in field and QWERTY keyboard appears. Selecting 'Enter' on keyboard will hide keyboard.

Confirmation

Back arrow: On selection user returns to payment screen (8.3).

On selection user is brought to screen with options to share flight summary. Available options based on device operating system and relevant apps installed on device.

On selection user is brought to list of bookings saved on the app.



On selection user is brought to screen with options to add to calendar. Available options based on operating system and relevant apps installed on device.

On selection user is brought to flight search screen (3.1).